



NetDelivery LaserJet 4 Device Driver Installation

Interbit Data, Inc.
251 West Central Street Natick, Massachusetts 01760 USA
(508) 647-0013 www.interbitdata.com

Disclaimer

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCTS ARE SET FORTH IN THE DOCUMENTATION PROVIDED TO YOU BY INTERBIT DATA AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY CONTACT YOUR INTERBIT DATA REPRESENTATIVE FOR A COPY.

Copyright 2010, Interbit Data Inc.

All rights reserved. Printed in the USA.

The information in this document is current as of the date listed in the revision table history.

Appendix Support

Technical Support	(508) 647-0013, ext. 4
Technical Support Direct	(508) 413 3087
email	https://interbitdata.com/contact/

Revision Table

Date	Description	Revision
06/24/2019	DRAFT	1.0
07/16/2019	Released	1.1
12/12/2019	Removed upgrade	1.2
07/06/2020	Updated logo	1.3
05/11/2021	Update	1.4
06/14/2021	Added 1.1	1.5
08/13/2021	Updated	1.6
10/21/2021	Added 2.1	1.7
03/17/2022	Updated	1.8

Companion Documentation

The following list of documentation can be accessed in the Interbit knowledgebase. The listed documentation goes deeper into specific configurations and topics of information.

Table 1-0 Companion Documentation

Part Number	Product	Description	Type
100-0227-00	NetDelivery	System Administration	Manual

Table of Contents

Table of Contents	6
1.0 Introduction	8
1.1 Intended Audience.....	8
2.0 Overview	9
2.1 Assign a NetDelivery Champion.....	9
3.0 Finding the device driver file	10
3.1 Microsoft catalog update website.....	11
4.0 Download the device driver file.....	12
5.0 Device driver.....	13
5.1 Device driver.....	14
5.2 Device driver.....	15
5.3 Creating a Temp folder	16
5.4 View Downloads	17
5.5 Open Folders.....	18
5.6 Downloaded file	19
5.7 Creating a Temp folder	20
5.8 Open Folder.....	21
5.9 Open Folder.....	22
6.0 Install the extracted device driver.....	23
6.1 Expanding the HP device driver	24
6.2 Expanding the HP device driver	25
6.3 Expanding the HP device driver	26
6.4 Expanding the HP device driver	27
6.5 Expanding the HP device driver	28
6.6 Expanding the HP device driver	29
7.0 Creating the printer.....	30
7.1 Add a Local or Network Printer.....	31
7.2 Select the type of printer, TCP/IP.....	32
7.3 Hostname or IP Address	33
7.4 Detecting TCP/IP port	34
7.5 Setup the port settings	35

7.6 Configure Standard TCP/IP port Monitor	36
7.7 Add a Printer.....	37
7.8 Select the device driver, HP LaserJet 4.....	38
7.9 Save the Printer	39
7.10 Printer Sharing	40
7.11 Add a Printer	41


1.0 Introduction

This document is for the following Interbit Data products, NetDelivery. This document explains the topic of HP LaserJet 4 device drivers.

1.1 Intended Audience

This document is for Interbit Data software application Users.

This diagram provides a brief overview of NetDelivery, and a description of the NetDelivery user interface and the administrative functionality accessible from the main menu.



2.0 Overview

This document is used to install the HP LaserJet 4 device driver.

2.1 Assign a NetDelivery Champion


A NetDelivery Champion is responsible for the NetDelivery software application at the customer site. The NetDelivery Champion is also responsible for communication with Interbit Data personnel, and regularly training users at the customer site. The NetDelivery Champion is responsible for all the sections in this document.

3.0 Finding the device driver file

1.0 Navigate to the HP LaserJet 4 website.

<https://www.catalog.update.microsoft.com/Home.aspx>


Screenshot 1-0 HP Laser Jet 4 Website



3.1 Microsoft catalog update website

1.0 Enter HP LaserJet 4 into the box.

Screenshot 1-1 HP LaserJet 4 Installation



4.0 Download the device driver file

1.0 Navigate to the Microsoft driver upload for HP LaserJet 4 device driver file.

2.0 Select the download icon.

Screenshot 1-2 Navigate to the Microsoft driver upload for HP LaserJet 4

Microsoft Update Catalog

Search results for "hp laserjet 4"

Updates: 1 - 25 of 994 (page 1 of 40)


Title	Products	Classification	Last Updated	Version	Size	Download
Microsoft driver update for HP LaserJet 4/4M Plus PS 300	Windows 7/Windows 8/Windows 8.1 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.4 MB	Download
Microsoft driver update for HP LaserJet 4/4M PS (300 dpi)	Windows 7/Windows 8/Windows 8.1 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.4 MB	Download
Microsoft driver update for HP LaserJet 4 Plus	Windows 7/Windows 8/Windows 8.1 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.4 MB	Download
Microsoft driver update for HP LaserJet 4/4M Plus PS 600	Windows 7/Windows 8/Windows 8.1 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.4 MB	Download
Microsoft driver update for HP LaserJet 4/4M PS	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	13.9 MB	Download
Microsoft driver update for HP LaserJet 4/4M PS (300 dpi)	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	13.9 MB	Download
Microsoft driver update for HP LaserJet 4/4M PS 300	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	13.9 MB	Download
Microsoft driver update for HP LaserJet 4 Plus	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	13.9 MB	Download
Microsoft driver update for HP LaserJet 4	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	13.9 MB	Download
Microsoft driver update for HP LaserJet 4/4M Plus PS 600	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	13.9 MB	Download
Microsoft driver update for HP LaserJet 4 Plus	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.6 MB	Download
Microsoft driver update for HP LaserJet 4	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.6 MB	Download
Microsoft driver update for HP LaserJet 4/4M Plus PS 600	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.6 MB	Download
Microsoft driver update for HP LaserJet 4/4M PS (300 dpi)	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.6 MB	Download
Microsoft driver update for HP LaserJet 4/4M PS	Windows 7/Windows 8/Windows 8.1 and later drivers; Windows Server 2008 R2; Windows Server 2012; Windows Server 2012 R2 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.6 MB	Download
Microsoft driver update for HP LaserJet 4	Windows 7/Windows 8/Windows 8.1 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.4 MB	Download
Microsoft driver update for HP LaserJet 4/4M PS	Windows 7/Windows 8/Windows 8.1 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.4 MB	Download
Microsoft driver update for HP LaserJet 4 Plus	Windows 7/Windows 8/Windows 8.1 and later drivers	Drivers (Printers)	6/21/2006	6.1.7233.0	11.4 MB	Download
Hewlett-Packard Company - Printers - Hp Color Laserjet 5500 PCL6	Windows 2000/Windows XP	Drivers (Printers)	11/6/2002	4.18.0.420	2.5 MB	Download
Hewlett-Packard Company - Printers - Hp Color Laserjet 5500 PCL6	Windows 2000/Windows XP	Drivers (Printers)	11/6/2002	4.18.0.420	2.5 MB	Download
Hewlett-Packard Company - Printers - Hp Color Laserjet 5500 PCL6	Windows 2000/Windows XP	Drivers (Printers)	11/6/2002	4.18.0.420	2.5 MB	Download
Hewlett-Packard Company - Printers - Hp Color Laserjet 5500 PCL3C	Windows 2000/Windows XP	Drivers (Printers)	9/19/2002	4.18.0.410	2.6 MB	Download
Hewlett-Packard Company - Printers - Hp Color Laserjet 5500 PCL3C	Windows 2000/Windows XP	Drivers (Printers)	9/19/2002	4.18.0.410	2.6 MB	Download
Hewlett-Packard Company - Printers - Hp Color Laserjet 5500 PCL3C	Windows 2000/Windows XP	Drivers (Printers)	9/19/2002	4.18.0.410	2.5 MB	Download

© 2019 Microsoft Corporation. All Rights Reserved. | privacy | terms of use | help

5.0 Device driver

1.0 Select the downloaded device driver file.


Screenshot 1-3 Device driver



5.2 Device driver

1.0 Verify the device driver file is downloaded.

Screenshot 1-5 Device driver




5.3 Creating a Temp folder

1.0 Navigate to This PC.

2.0 Create a new folder called Temp.

3.0 Click the Save icon button.


Screenshot 1-6 Creating a Temp Folder



5.4 View Downloads

1.0 Select the View Downloads button.


Screenshot 1-7 View Downloads



5.5 Open Folders

1.0 Click the Open Folders button.


Screenshot 1-8 Open Folders



5.6 Downloaded file

1.0 Select the downloaded file.

Screenshot 1-9 Downloaded file



Note: You cannot use windows to unzip the cab file. You must use a program like 7-ZIP.


5.7 Creating a Temp folder

1.0 Navigate to This PC.

2.0 Create a new folder called Temp.

3.0 Click the Save icon button.


Screenshot 1-10 Creating a Temp Folder



5.8 Open Folder

1.0 After the file downloads file select the Open Folder button.


Screenshot 1-11 Open Folder icon



5.9 Open Folder

1.0 Verify the file is downloaded to the Temp folder.


Screenshot 1-12 Open Folder



6.0 Install the extracted device driver

1.0 Expanding the device driver in the Temp file.


Screenshot 1-13 Expanding the HP device driver



6.1 Expanding the HP device driver

1.0 Enter the following command from the C:\temp> expand -R 4188_bacd1413e93b46362d9a2ca653c869f1c02f6f7.cab hpdriver -F*


Screenshot 1-14 Expanding the HP device driver



6.2 Expanding the HP device driver

1.0 Verify the file is expanding in the C:\temp folder.


Screenshot 1-15 Expanding the HP device driver



6.3 Expanding the HP device driver

1.0 Verify the file is expanded and the console is at the C:\temp>

Screenshot 1-16 Expanding the HP device driver




6.4 Expanding the HP device driver

1.0 Navigate to the prnhp001 file.

2.0 Right click on the prnhp001 file.

3.0 Select install.


Screenshot 1-17 Expanding the HP device driver



6.5 Expanding the HP device driver

1.0 Select yes to install the HP drivers.

Screenshot 1-18 Expanding the HP device driver




6.6 Expanding the HP device driver

1.0 Click the OK button.

2.0 The HP device driver installation is complete.


Screenshot 1-19 Expanding the HP device driver



7.0 Creating the printer

1.0 Navigate to the Control Panel to Add a Printer.


Screenshot 1-20 Creating the printer



7.1 Add a Local or Network Printer

1.0 Select Add a Local or Network Printer.

Screenshot 1-21 Adding a Local or Network Printer




7.2 Select the type of printer, TCP/IP

1.0 Select Add a printer using a TCP/IP address or hostname.

2.0 Click the Next button.

Screenshot 1-22 Select the type of printer, TCP/IP




7.3 Hostname or IP Address

1.0 Enter the Hostname or IP Address local host.

2.0 Click the Next button.


Screenshot 1-23 Hostname or IP Address



7.4 Detecting TCP/IP port

1.0 Click the cancel button.


Screenshot 1-24 Detecting TCP/IP port



7.5 Setup the port settings

1.0 Click the Custom Settings button.


Screenshot 1-25 Setup the port settings



7.6 Configure Standard TCP/IP port Monitor

1.0 Click the OK button after you verify the Port Name and Printer Name.

Screenshot 1-26 Configure Standard TCP/IP port Monitor




7.7 Add a Printer

1.0 Click the Custom button.

2.0 Click the Settings button.

Screenshot 1-27 Adding a Printer




7.8 Select the device driver, HP LaserJet 4

1.0 Select HP Manufacturer.

2.0 Select HP Laser Jet 4 Printer.

Screenshot 1-28 Select the device driver, HP LaserJet 4




7.9 Save the Printer

1.0 Enter the name of the printer.

2.0 Click the Next button.

Screenshot 1-29 Save the Printer




7.10 Printer Sharing

1.0 Select Do not share this printer.

2.0 Click the Next button.

Screenshot 1-30 Printer Sharing



7.11 Add a Printer

1.0 Deselect the Set as the default printer check box.

2.0 Click the Finish button.

Screenshot 1-31 Adding a Printer

